

VERTIVTM

Albér Battery Xplorer

Release Notes

VERSION 3.6.9.16, OCTOBER 5, 2018

Release Notes Section Outline

- 1 Updates for This Release (Version 3.6.9.16)
- 2 Version 3.6.8.14 Update Information
- 3 Version 3.5.8.4 Update Information
- 4 Version 3.3.7.2 Update Information
- 5 Version 3.3.7.1 Update Information
- 6 Version 3.2.7.21 (Controlled Release) Update Information
- 7 Version 3.2.7.20 Update Information
- 8 Version 3.1.187 Update Information

1 Updates for This Release (Version 3.6.9.16)

This release is now compatible with the new UXCM version 3.4.9.12 firmware.

2 Version 3.6.8.14 Update Information

- Details and Trends reports configuration screens no longer obstruct reports.
- Added cell temperature support for the UXCT.
- Resolved issues with offline view battery page ambient temperature display.
- · Postal codes were updated for internationalization.
- Changed cell bars to no longer remain green (normal) when alarm is latched; they now show color.

3 Version 3.5.8.4 Update Information

- Preventive maintenance reports now available.
- UXCM backup viewing now available offline.
- Inter-tier maximum number is now increased to 96.
- Commissioning report enhancements and improvements added.
- The correct installation date is now shown in the discharge report.
- The Commissioning report now has a section for system parameters (overall voltage, ambient temperatures and currents).
- Added support of new UXBM-50 string configuration (075) 48x12V, 12 shelves of 4 jars, or 12S of 4J.
- Version and model number on the commissioning report is no longer truncated.

4 Version 3.3.7.2 Update Information

This release added new configuration #074 to the XML file to support 36x12V, 6 shelves of 6 jars, or 6S of 6J.

5 Version 3.3.7.1 Update Information

Added license agreement to the installer.



- Added two new configurations for 1x41x12V and 1x34x12V.
- Inter-tier alarms are now reported even when intercell optional parameter is disabled.
- String commissioning reports names are now improved to help distinguish reports on customer sites.

6 Version 3.2.7.21 (Controlled Release) Update Information

- Reports now support European date formats.
- · Detail cell report now shows all cells.
- String commission reports now populate all device information.

7 Version 3.2.7.20 Update Information

- Corrected discharge overall voltage unit displayed (V).
- Discharge current highlighting shows correctly for a high negative discharge current.
- · Discharge playback enhancements.
- Enhanced thermal runaway user interface.
- Velocity client login improvements for multiple clients/network connections.
- Velocity client improvements to support multiple connections from the same network card/computer.
- USB connection enhancements.
- Added battery and string information to commissioning report filenames.
- Reports no longer freeze when exporting to PDF and XLS.

8 Version 3.1.187 Update Information

INTERNAL REF#	UPDATE DESCRIPTION
[2441]	Tag ID under hardware view now displays correct information.
[2462]	Changed description for hardware configuration number 013 to 3 shelves of 8 jars and 2 shelves of 4 jars on setup wizard.
[2475]	Removed configuration for hardware configuration numbers 027 and 030 on setup wizard to avoid confusion of having two listings for 32X12V open rack systems in drop-down listing.
[2507]	Added new open rack configurations for setup wizard: 42X12, 44X12, 48X12, and 50X12.
[2520]	Improved the displaying of pie charts on battery view to avoid access violation errors by only creating the needed pie charts instead of loading all charts possible before displaying.
[2526]	Added warning message for user to select a hardware node when assigning strings to hardware if none are selected.
[2527]	String validation wizard no longer requires Ambient Temp 2 to be enabled to complete validation.
[2557]	Installer now includes all latest firmware available at release time.
[2561]	Added "all" and "none" selection buttons and fixed overall voltage and string current values on discharge report.
[2562]	Ambient Temperature readings now display correct value (N/A) when temperature is not available.
[2573]	Ambient Temperature reading on discharge playback now displays N/A for a value if it is enabled and not connected; it used to display 10996.5 F.

© 2018 Vertiv Co. All rights reserved. Vertiv and the Vertiv logo are trademarks or registered trademarks of Vertiv Co. All other names and logos referred to are trade names, trademarks or registered trademarks of their respective owners. While every precaution has been taken to ensure accuracy and completeness herein, Vertiv Co. assumes no responsibility, and disclaims all liability, for damages resulting from use of this information or for any errors or omissions. Specifications are subject to change without notice.